

Adding a new Label or barcode settings

SenangUrus ERP comes with some commonly used barcode configurations for you our-of-box. If your barcode configuration isn't covered then you can easily create a new configuration.

The screenshot shows the 'Add barcode sticker setting' form in the Vault Space ERP system. The form is titled 'Add barcode sticker setting' and is located in the 'Settings' section of the application. The form includes the following fields and options:

- Sticker Sheet setting Name:** A text input field with the placeholder 'Sticker Sheet setting Name'.
- Sticker Sheet setting Description:** A text area with the placeholder 'Sticker Sheet setting Description'.
- Continuous feed or rolls**
- Additional top margin (In Inches):*** A numeric input field with a value of 0.
- Additional left margin (In Inches):*** A numeric input field with a value of 0.
- Width of sticker (In Inches):*** A numeric input field with a value of 0.
- Height of sticker (In Inches):*** A numeric input field with a value of 0.
- Paper width (In Inches):*** A numeric input field with a value of 0.
- Paper height (In Inches):*** A numeric input field with a value of 0.
- Stickers in one row:*** A numeric input field with a value of 0.
- Distance between two rows (In Inches):*** A numeric input field with a value of 0.
- Distance between two columns (In Inches):*** A numeric input field with a value of 0.
- No. of Stickers per sheet:*** A numeric input field with a value of 0.
- Set as default**

A 'Save' button is located at the bottom right of the form.

You must have all measurement details of the sticker to create a configuration. All dimensions need to be in inches.

Adding Barcode sticker settings

1. Go to settings -> Barcode Settings -> Add
2. Enter a descriptive name of the setting. Add some description for your information.
3. If you're using a Roll, then check the "Continues feed or rolls" checkbox.
4. Enter Additional top margin (In Inches), Additional left margin (In Inches), width of the sticker, Height of the sticker, Paper width, Paper height, number of stickers in one row, distance between 2 rows, distance between 2 columns and the total number of stickers per sheet.
5. Some of this information are not needed for Continues feed or rolls.

You **must** test you setting by printing a dummy sticker in Purchase – print label option. If something seems wrong then edit the measurement accordingly.

Revision #2

Created 30 September 2025 04:24:33 by Admin

Updated 13 October 2025 14:28:34 by Admin